

Hoppie Datalink Plugin for EuroScope

Green = Connected
 Red = Error
 (see chat or first Line in Data-Part for error)

Click to reduce Window to upper Bar
 Hold to drag Window

Left-Click to close Window
 (type `.cpdlc` to open it again)
 Right-Click to Connect to Hoppie Network

DATALINK

BOE1	H	/	S	/	V	/	TOD	R
AIB1	H	/	S	/	V	/	TOD	R

AIB1
 L WCO/CLMB 410/RF 410/WCO/CLMB 390/
 R RD WRB/
 V
 T

LVL	ROUTE	VCI	SSR	MIKE
-----	-------	-----	-----	------

← Aircraft List
 Click Entry to Select

CLIMB

DESCEND

MAINTN

MAX ROC

MIN ROC

EXECUTE

CONT HDG

FLY HDG

DCT TO

TURN L DEG

TURN R DEG

EXECUTE

DIM

BRIGHT

CNTCT Δ

MAN LOGOFF

UPL NSSR

SQWK IDENT

START AUTO

CURR AC

ALL AC

CHAT COMMANDS:
 Open Window (if closed):
`.datalink`

Manually Set Callsign:
`.datalink [CALLSIGN]`

Automatically generate Callsign:
 (default)
`.datalink AUTO`

1 INSTALLATION


After downloading the zip-file, extract the files included into any Folder of your choice.

Now you have to add your Hoppie Login Code the `datalink.ini` File by changing the following line:

```
logonCode=YOUR_LOGON_CODE
```

Replace "YOUR_LOGON_CODE" with the Code you obtain here: <http://www.hoppie.nl/acars/system/register.html>

Once you successfully loaded the Plugin into EuroScope (Other SET -> Plug-ins) and allowed it to draw on EuroScope's "Standard ES radar screen"



You should see the following Window on your Main Radar Screen:



2 USAGE - LOGIN

The Application will automatically determine your Hoppie Callsign, if you are connected on one of the following Facility Types:
APP/DEP, CTR or FSS

You will find your Callsign in your EuroScope Chat.

If you want to use your own Callsign, aren't connected to Vatsim or connected to Vatsim but on none of the above Facility Types (e.g. TWR, GND or DEL),

You can override the automatically determined Callsign by using the following Chat Command:

```
.datalink [CALLSIGN] | .cpdlc [CALLSIGN]
```

To let the Plugin decide your Callsign again, use:

```
.datalink AUTO | .cpdlc AUTO
```

AFTER you or the Plugin determined a Callsign, you can login to Hoppie's Network by RIGHT-CLICKING the X in the top-right Corner of the Program.

The Grey "DATALINK"-Header will turn Green, if you are successfully connected.

If, for some reason, the Plugin couldn't establish a successful connection, the Header will turn Red and you will see an Error Message in the first Line after the Aircraft List. (see arrow above)

The Buttons on the bottom of the Window will remain non-clickable, until an Aircraft is connected to your Station.

3 USAGE – YOUR FIRST AIRCRAFT

Once an Aircraft tries to Logon to your Station, your Window will change to this:



Now you have several Options on the Bottom of the Window.

You can either:

ACC – Accept the Aircraft

SBY – Send it a Standby Message

UNA – Dismiss its Logon Request with an Unable Message

UDT – same as UNA but with the Reason “Due to Traffic”

UDA – same as UNA but with the Reason “Due to Airspace”

Once you accepted the Aircraft you have several Options



You can currently send:

LVL - Flight Level Changes (Climb/Descend)

ROUTE – Route Changes (HDG, TURN, DIRECT)


VCI – Handoff Instructions or manually force the Aircraft to log off

SSR – Squawk Ident and set Squawk Instructions

MIKE – Mike Check Instructions

4 USAGE - REQUESTS

Pilots can currently request a new Flightlevel (RF) or a Direct (RD).



You have the following Options to answer such a Request (found in the LVL submenu):

CLIMB [FL]

DESCEND [FL]

MAINTN [FL]

STANDBY

UNABLE

Direct Requests can be answered with (found in the ROUTE submenu):

CONTINUE PRESENT HEADING

FLY [HDG]

DCT TO [WAYPOINT]

STANDBY

UNABLE

5 ABBREVIATIONS

- CNTCT – Contact [freq] (+automatic Datalink Handoff to next Station, if online)
- MIKE – Check Stuck Mic Instructions
- RD – Request Direct
- RF – Request Flight Level
- SBY – Standby
- SSR – Secondary Surveillance Radar (Code) / Squawk Code
- NSSR – Next/New SSR Code
- UNA – Unable
- UDT – Unable Due to Traffic
- UDA – Unable Due to Airspace
- VCI – Voice Change Instructions
- WCO – Wilco, Message Understood and Will Comply